


# Usage and Information for the Disking Repair USB



## Location of Programs:

The full path to a folder containing 1 or more programs to be seen in the program. The program must be of the type "exe, bat, cmd or lnk (a shortcut)". Any file can be made into a shortcut and this technique can be used if you wanted to launch some other file type such as a pdf or .doc

## Location of Icons:

This must be the full path to a folder containing .ico files for each program you want an image for. Each icon file has to either have the same first word (separated by a space, Eg. "Example Program.exe" would be "example.ico." Or full file name, Eg. "example program.exe" NOTHING INBETWEEN. None of this is cap sensitive.


## More on Icons:


Icons are generated when "generate icons" is clicked. The icon name is then written to the settings file. If you have populated a folder with icons yourself, or changed the name of an icon and program recently simply go into settings and then click "save and exit" or click the "restart" button at the top, this will go and rescan your icon directory and update the icon names in the JSON file.

## Generate Icons:

This will scan through the specified locations and pull icons from the programs found. These will then get saved to a folder in the launch directory. If a program file cannot get pulled it is most likely due to it being a windows store app or an app installed in a special "protected" way. You will have to obtain your own icons if this is the case.

Regenerated icons will not replace old icons, just generate ones for any new programs. Delete an old icon to get it replaced





View more details shows more details about the app (normally user specified)

Edit details drops you straight into the edit screen (although this can also be accessed through more details)

Add to favourites... Adds to favourites

Disking Repair USB

### Application Information

File Name:

Disp Name:

Short Description:

Long Description:

Tags:

File name is the actual file name on disk, changing this changes it on disk. (Max length 64 characters, cannot contain ? : \ / < > " )

Disp name is the display name, the name that gets shown below the icon in image view (Max 12 characters)

Short description is what appears when you hover over a program entry, this will get auto entered if there were brackets in the file name. (Max 64 characters)

Long description can only be viewed in the more settings menu. (Max 512 characters)

Tags is a series of tags you could assign to certain programs (Eg. Antivirus, drivers, data recovery). These tags can be searched in the search bar, separate each tag with a comma (Max 256 char limit)

Right clicking on the program in the task bar will bring up your quick actions. Most of the programs you have in your favourites should appear in your quick access options and can be launched right from there!

